

Torque

How do I migrate server settings to a new server, and retain the job numbering?

Issue: Need to migrate Torque to a new server, yet continue the job numbering

Affected Version: All Versions

Problem: The server running Torque is being replaced, and the job numbering needs to continue rather than start over.

Solution: The steps to migrate Torque include capturing the configuration, and separately capturing the next job ID, then restoring those to the new server. Here's the procedure:

1. On the older server, capture the qmgr settings from the output of: `qmgr -c 'p s'`
2. Shut down `pbs_server` (again on the old server) and view the `<Torque Home>/server_priv/serverdb` file. Note the value for the "`<nextjobid>`" XML element.
3. Once Torque has been installed on the new server, bring up `pbs_server` and redirect the output from step 1 into `qmgr` (with `pbs_server` running).
4. Shut down `pbs_server` (via `qterm` or `init` script)
5. Edit the file `<Torque Home>/server_priv/serverdb` -- change the `<nextjobid>` element to the job ID you recorded from the old server.
6. Start `pbs_server`

Note that this procedure does not address migrating jobs. That is covered in another KB article.

Unique solution ID: #1192

Author: Rob Greenbank

Last update: 2018-01-19 19:54